


System Toolbar

Browser Controls

Navigator


- Model Tree
- Folder Browser
- Favorites
- History
- Connections
- Search



Feature Toolbars







Datum		Plane
		Axis
		Curve
		Sketches
		Point
		Coordinate system
Pick/Place		Analysis
		Hole
		Shell
		Rib
		Draft
		Round
Base		Chamfer
		Extrude
		Revolve
		Variable section sweep
		Boundary blend
		Style
Editing		Copy
		Mirror
		Move
		Merge
		Trim
		Pattern

Dashboard









Selection

Mouse Controls




ACTION		RESULT	COLORS
Move Pointer		Items under pointer are highlighted	 <pre> Preselection highlight (Cyan) Selected (Bright Red) Secondary selected (Orange) Preview geometry (Yellow) Secondary preview geometry (Pale Yellow) </pre>
Right-click		Items under the pointer are query highlighted	
Left-click		Highlighted item is selected	
CTRL + 		Add/Remove items	
SHIFT + 		Select chain or surface set	

Direct Viewing

Mouse Controls

3D Modes	(Drag MMB)	2D Modes	
SPIN		PAN	
PAN	SHIFT + 	ZOOM	CTRL + 
ZOOM	CTRL + 		
TURN	CTRL + 		

Wheel Mouse Controls

ZOOM	
Quick-zooming with a wheel mouse	
SHIFT + 	.5x
CTRL + 	2x



Spin Center

Enabled: Icon = Spin Center
Disabled: Cursor = Spin Center




View Mode

Allows DELAYED and VELOCITY Viewing Modes

Shortcut tip: Use CTRL-SHIFT-MMB to enable/disable view mode

Selection


Selection Geometry








Using the Smart Filter

Feature First, Geometry Second





Moving between Features and Geometry is fast and easy with the Smart filter. First, select one or more features. Perform an action on the selected feature(s) or proceed to select some geometry of that feature.







Snapping

				
Press LMB and begin dragging	Holding SHIFT	Move pointer over reference geometry	Release LMB, Release SHIFT	Handle is snapped, handle appearance changes to indicate snapping
Handle stretches from anchor point and is highlighted (filled black) while dragging	White 'snap indicator' circle appears on the drag handle	Reference geometry is highlighted (cyan)	Geometry is selected as reference	Anchor point and extendor arm will disappear, leaving handle with black 'snap' circle

Unsnapping

			
Holding SHIFT	Move pointer over handle	Drag handle off reference geometry	Release
Snapped handle is 'at rest'	Reference geometry is highlighted	White 'snap indicator' circle disappears from the handle	Handle is unsnapped and reverts to its original state

Copying for Variable Features

			
Move pointer over anchor to copy	Press and hold LMB Press and hold CTRL	Dragging from anchor copies and places the new handle	Release
The anchor point is highlighted	The sequence of mouse/keyboard commands is important	Original handle is unchanged, while dragging new copy	